



Sibelius

Sibelius 5

Licence Server User Guide

Edition 5.1

November 2007

Booklet written by Daniel Spreadbury, Andrew Pearson and Richard Payne.

Sibelius Licence Server copyright © 2001–2007 Sibelius Software, a division of Avid Technology, Inc.

The Sibelius Licence Server constitutes part of the Sibelius Product and is subject to the Sibelius licence agreement, supplied with Sibelius or available on request. You are not licenced to install or use the Sibelius Licence Server unless you are a registered Sibelius network version user.

Contents

Introduction to network site licences	4
Installing and upgrading	5
Installation on Windows	7
Installation on Mac OS X	10
Upgrading on Windows	13
Upgrading on Mac OS X	15
Installing Sibelius	16
Configuring and using the Licence Server	19
Configuring the Licence Server	21
Registering the Licence Server	23
Testing the Licence Server	27
Access Control	29
Working with clients	31
Reading logs	33
Maintaining the Licence Server	35
Troubleshooting	37
Appendices	41
Appendix A: Starting or stopping the Licence Server	43
Appendix B: Manually configuring the Licence Server	45
Appendix C: Manually locating Licence Server logs	48
Appendix D: Licence Server commands	49
Appendix E: Licence Server error codes	51
Appendix F: Useful command line commands	52

Introduction to network site licences

Two types of Sibelius site licence are available: stand-alone site licences and network site licences. You have purchased a network site licence for a fixed number of copies.

Sibelius's network version operates on a *client-server* model. The *client* is the Sibelius program itself, which is installed on the local hard drive of each of the student workstations, and the *server* is the separate Licence Server program, which is installed on a single designated server or workstation.

The Licence Server enables the designated number of licenced client copies to run on the network simultaneously. It also lets you send messages to users of the client copies, and close copies down from the server machine.

The Licence Server itself does not have a graphical user interface, because it runs in the background, listening to requests from client copies of Sibelius on the network. The server is therefore configured and managed using the graphical Licence Server Control Panel, which you can run either on the computer on which the Licence Server is installed, or from another workstation.

The Licence Server and Licence Server Control Panel programs are supplied on a separate CD-ROM from the Sibelius program itself.

Requirements

The Sibelius Licence Server and the Licence Server Control Panel will run on Windows XP, Windows 2003 Server, Windows Vista 32-bit, Mac OS X 10.4 or later, Mac OS X Server 10.4 or later, or on an Apple Xserve running Mac OS X 10.4 or later.

Sibelius requires a network using the TCP/IP protocol. (Your network may use other protocols in addition to TCP/IP, but TCP/IP must be present in order for the Licence Server to communicate with the client copies.)

If you use a firewall on your network, ensure that port 7312 is open both for TCP/IP and UDP traffic.

If you use a Novell network, note that you cannot install the Sibelius Licence Server onto a server running Novell Netware. The Licence Server can only be run on Windows or Mac OS X servers or workstations. To run Sibelius on a Novell network, you will need to install the Licence Server program on a suitable Windows or Mac OS X workstation.


Installing and upgrading

Installation on Windows


If you are upgrading your Licence Server from any earlier version of Sibelius (including Sibelius 5.0), see **Upgrading on Windows** on page 13.

Installing the Licence Server

- Insert the Sibelius Licence Server CD-ROM, and if installation does not begin automatically, open a window onto the contents of the disc using My Computer or Windows Explorer, then double-click LicenceServerInstaller.msi to start the installation.
- You will see the following window:




- Click **Next**.
- Next you will be asked if you want to install the Windows service:



Unless you are intending to install the Control Panel only on this computer (because you have already installed the Licence Server itself on another machine), you should leave the **Install Windows service for Licence Server** option switched on, then click **Next**.

- Now you will be prompted to choose an installation folder:




By default, the Licence Server will be installed to the folder **C:\Program Files\Sibelius Software\Sibelius 5 Licence Server**, but you can change this if you wish by clicking **Browse**. Make sure that the Administrator group of users has full read and write access to the folder you have chosen. If your chosen folder does not exist, the installer will create it for you.

On RM Community Connect 3 (CC3) systems, we recommend installing the Licence Server in the RM Public folder, as this has no restrictions, ensuring that no permissions problems will be encountered.

Once you have determined where the Licence Server should be installed, click **Next**.

- You are told that the installer is ready:



Click **Next**.

- You will see a progress bar as the Licence Server and Control Panel are installed. If you have a firewall active, you may see a window appear telling you that the program **LicenceServerV5.exe** is trying to access the Internet: this is normal and happens when the Windows service is started for the first time. Choose whichever option tells your firewall that this program is safe to access the Internet.

Depending on the specific firewall you are using, you may not receive a notification at this point, in which case you should now go to your firewall's control panel and open port 7312 for both TCP and UDP traffic.

- After a few moments, you will be told that installation has completed successfully. Click **Close** to exit the installer.

Configuring and using the Licence Server

Now see **Configuring the Licence Server** on page 21.

Installing Sibelius on the client computers

Once you have installed and configured the Licence Server, you need to install the Sibelius application on each client machine you want to use with the Licence Server: see **Installing Sibelius** on page 16.

Uninstalling the Licence Server

If you need to uninstall the Licence Server (e.g. to upgrade it, or to install it on another computer), do so as follows:

- Choose **Start ▶ Control Panel**, then double-click **Add/Remove Programs** (Windows XP) or **Programs and Features** (Windows Vista).
- In the list of installed programs, select **Sibelius Licence Server**, and click **Add/Remove** (Windows XP) or **Uninstall** (Windows Vista).
- Follow the on-screen prompts to uninstall the Sibelius Licence Server.

Once the Licence Server has been uninstalled, the registration data is also removed, and if you subsequently reinstall the Licence Server on the same computer, you will have to re-register and reconfigure it.

Installation on Mac OS X

If you are upgrading your Licence Server from any earlier version of Sibelius (including Sibelius 5.0), see **Upgrading on Mac OS X** on page 15.

Installing the Licence Server

The Licence Server and the associated Control Panel application should be installed to the **Applications** folder on your Mac's system volume, and scripts are installed in the **/Library/StartupItems** folder so that the Licence Server starts automatically when your computer starts up.

The provided installer will install all the files to the correct locations, and you are strongly recommended to accept the default locations. If you want to install the Licence Server to another location on your computer, you will have to manually edit the scripts in **/Library/StartupItems** and **/Applications/Sibelius 5 Licence Server** after installation. This is not something that inexperienced network administrators should attempt!


To perform the standard, recommended installation:

- Insert the Licence Server CD-ROM. A window should appear showing two icons: double-click **Install Sibelius Licence Server** to begin.
- The following window will appear:




Click **Continue** to proceed.

- Next, you are told that the installer will perform a standard installation:




On Mac OS X 10.5 Leopard, you will see a button **Change Install Location**, which you can use to choose on which volume to install the Licence Server; however, as stated above, you are strongly recommended to install the software on your Mac's system volume. So just click **Install**.

- You are now prompted to provide an administrator username and password: do so, and click **OK**.
- Next you will see a progress bar as the files are installed to your Mac's hard disk:



- After a few moments, you will be told that the installation has completed successfully.



- Click Close to exit the installation.

Configuring and using the Licence Server

Now see **Configuring the Licence Server** on page 21.

Installing Sibelius on the client computers

Once you have installed and configured the Licence Server, you need to install the Sibelius application on each client machine you want to use with the Licence Server: see **Installing Sibelius** on page 16.

Uninstalling the Licence Server

To uninstall the Licence Server:

- Run Terminal, which you can find in /Applications/Utilities.
- Type `sudo /Applications/Sibelius\ 5\ Licence\ Server/uninstall.sh` and hit Return.
- You will be prompted to provide your administrator password: do so and hit Return.
- You will see a few messages output to the Terminal window as the Licence Server is shut down and deleted.

Once the Licence Server has been uninstalled, the registration data is also removed, and if you subsequently reinstall the Licence Server on the same computer, you will have to re-register and reconfigure it.

Upgrading on Windows

To upgrade your network site licence from Sibelius 1.4, Sibelius 2, Sibelius 3 or Sibelius 4 or Sibelius 5.0 to Sibelius 5.1, you will need to upgrade both the Licence Server and all the client machines.

Upgrading from Sibelius 4 or earlier

- Quit the Licence Server on the computer on which it is installed, referring to the appropriate booklet.
- If you have the Licence Server installed as a Windows service, uninstall it:
 - *For Sibelius 1, 2 and 3:* go to the Licence Server console and type **uninstall**
 - *For Sibelius 4:* open a command window (on Windows XP, choose **Start ▶ Run**, then type **cmd** and hit **Return**; on Windows Vista, click **Start**, type **cmd** and hit **Return**), navigate to the folder that contains the Licence Server and type:

```
LicenceServerV4 -v -uninstall
```

It is very important to uninstall the service in the correct way to avoid leaving a service that can't be removed.

- Delete the folder containing the Licence Server to avoid confusion with the later version.

Upgrading from Sibelius 5.0

If you are upgrading from Sibelius 5.0 to Sibelius 5.1, upgrade the Licence Server first, as Sibelius 5.0 clients can run with the Sibelius 5.1 Licence Server, but Sibelius 5.1 clients cannot run with the Sibelius 5.0 Licence Server.

- Quit the Licence Server on the computer on which it is installed, referring to the appropriate booklet.
- If you have the Licence Server installed as a Windows service, uninstall it:
 - Open a command window (on Windows XP, choose **Start ▶ Run**, then type **cmd** and hit **Return**; on Windows Vista, click **Start**, type **cmd** and hit **Return**)
 - Navigate to the folder that contains the Licence Server and type:

```
LicenceServerV5 -v -uninstall
```

It is very important to uninstall the service in the correct way to avoid leaving a service that can't be removed.

- Delete the Registry keys in **HKEY_LOCAL_MACHINE\Software\Sibelius Software\Licence Server 5**:
 - First, run the Registry Editor (on Windows XP, choose **Start ▶ Run**, then type **regedit** and hit **Return**; on Windows Vista, click **Start**, type **regedit** and hit **Return**), and navigate to this location.
 - Select the Licence Server 5 folder, hit **Delete**, then click **Yes**.
- Install, register, configure and run the latest version of the Licence Server according to the instructions in **Installation on Windows** on page 7.

Upgrading the client machines

To upgrade each of the client machines, use the Sibelius 5 DVD-ROM (not the Licence Server CD-ROM) and follow the instructions described in the **Upgrading to Sibelius 5** booklet.

When you first run Sibelius 5.1, the splash screen will say **UNREGISTERED COPY** as the program is loading (because at that point it has not yet been registered by the Licence Server over the network), and will then change to say **Registered to Network User** once the program is given permission to run by the Licence Server.

Running two Licence Servers

The Sibelius 5.1 Licence Server, the Sibelius 4 Licence Server and the revised Sibelius 3 Licence Server may be run simultaneously on the same server and installed concurrently.

If you need to do this, it will be necessary to change the port number used by one of the licence servers. When signing on a client copy for the first time to a licence server with a different port number, the syntax for the server IP address will be, for example, **192.168.1.183:8989** (where **8989** is whatever new port you have chosen).

If you do not have the most up-to-date Sibelius 3 or 4 Licence Server, visit:

<http://www.sibelius.com/helpcenter/upgrades.html#network>

to download the latest version.

Upgrading on Mac OS X

To upgrade your network site licence from Sibelius 1.4, Sibelius 2, Sibelius 3 or Sibelius 4 or Sibelius 5.0 to Sibelius 5.1, you will need to upgrade both the Licence Server and all the client machines.

If you are upgrading from Sibelius 5.0 to Sibelius 5.1, upgrade the Licence Server first, as Sibelius 5.0 clients can run with the Sibelius 5.1 Licence Server, but Sibelius 5.1 clients cannot run with the Sibelius 5.0 Licence Server.

Upgrading the Licence Server

- Run Terminal, change to the root user (`sudo bash -login`), navigate to the folder that contains the Licence Server (`cd /usr/local/bin`) and run the script called `stop_licence_server` (`./stop_licence_server`).
- If you have set the old version of the Licence Server to run on start-up, e.g. by specifying that it should run in `/etc/rc.local`, you should also disable this. You can disable the line in question simply by adding a `#` character at the start of the line. If you followed the instructions supplied with the previous version, the line probably looks like this:

```
/usr/local/bin/start_licence_server
```

 so edit it so that it looks like this:

```
# /usr/local/bin/start_licence_server
```
- You should also delete the old Licence Server executable and the three associated scripts. Again, these will normally be found in `/usr/local/bin`.
- Install, register, configure and run the Licence Server according to the instructions in **Installation on Mac OS X** on page 10.

Upgrading the client machines

To upgrade each of the client machines, use the Sibelius 5 DVD-ROM (not the Licence Server CD-ROM) and follow the instructions described in the **Upgrading to Sibelius 5** booklet.

When you first run Sibelius 5.1, the splash screen will say **UNREGISTERED COPY** as the program is loading (because at that point it has not yet been registered by the Licence Server over the network), and will then change to say **Registered to Network User** once the program is given permission to run by the Licence Server.

Running two Licence Servers

The Sibelius 5.1 Licence Server, the Sibelius 4 Licence Server and the revised Sibelius 3 Licence Server may be run simultaneously on the same server and installed concurrently.

If you need to do this, it will be necessary to change the port number used by one of the licence servers. When signing on a client copy for the first time to a licence server with a different port number, the syntax for the server IP address will be, for example, `192.168.1.183:8989` (where `8989` is whatever new port you have chosen).

If you do not have the most up-to-date Sibelius 3 or 4 Licence Server, visit:

<http://www.sibelius.com/helpcenter/upgrades.html#network>

to download the latest version.

Installing Sibelius

Example scores

Before you install Sibelius, you should liaise with your music staff or network administrators about the best place to install Sibelius's example scores.

- On Windows, Sibelius installs the example scores into a folder called **Example Scores** inside the **Sibelius 5** program folder, and creates a shortcut to this folder inside the **My Documents** folder belonging to the current user. If you want to make these files available to all users, you should manually copy the **Example Scores** folder to an appropriate location on the network.
- On Mac, you should copy the **Example Scores** folder from the Sibelius 5 DVD-ROM to an appropriate location on the network, if you want to make these files available to all users.

Installing Sibelius on your client machines

Install Sibelius on each of your client machines following the instructions in your Handbook, using the same serial number (starting SCEW, SWEW, or SCEG) that you used to install and register the Licence Server (you don't need to register the client copies).

It is essential that Sibelius be installed on the local hard disk of each client machine. *It cannot be installed on a network drive or a virtual disk.*

You can install Sibelius on all the client computers using the same serial number; as long as all your computers are connected on the same network via TCP/IP and can thus see the machine running the Licence Server, they can share the same licence.

You can install Sibelius on as many computers as you like, but it will only allow as many copies as are licenced to be run simultaneously; you could install Sibelius on 30 computers, but if you only have a licence for 10 copies, only 10 copies will be able to run simultaneously.

Note that, regardless of how many copies you have bought, you will only receive one installation DVD-ROM and serial number, valid for the appropriate number of licences purchased.

Running for the first time

When you run each client copy of Sibelius for the first time, you will be prompted for the location of the machine running the Licence Server. You should supply this information as an IP address (e.g. 192.168.1.100) or you can specify the server name (e.g. **server**).

You can also enter the port on which the Licence Server is running (e.g. 192.168.1.100:8989) (although there is no need to do this unless you have explicitly changed it when setting up the Licence Server – see **Configuring the Licence Server** on page 21).

This information is stored on the client computer and does not need to be entered again.

Sibelius will then contact the server in order to get permission to run. If the maximum number of licenced copies has not been exceeded, it will start up and run normally. If the maximum number of copies has been reached, a message will inform you of this and Sibelius will quit.

As the networked copies of Sibelius run, they remain in contact with the server, which maintains a list of copies running. Should a client machine crash or become disconnected for some reason, the

Licence Server will remove that copy from the list. If a copy of Sibelius cannot contact the Licence Server, it will quit, allowing the user to save their work first.

Setting the Licence Server address automatically on Windows

To avoid typing the Licence Server address into each client copy of Sibelius individually, you can deploy it to all the client machines by way of a Registry key.

Inside the installation folder (C:\Program Files\Sibelius Software\Sibelius 5 Licence Server by default) you will find a file called `SibeliusClientSettings.reg`. This is a template Registry key and you *must* edit it before you use it!

Right-click on the `SibeliusClientSettings.reg` file and choose Edit, which will open the file in Notepad. You should only change the text between the quotation marks on the lines that look like `@=""`.

- To change the application path from the default, edit:

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Sibelius Software\Sibelius 5\ApplicationPath]
@="C:\Program Files\Sibelius Software\Sibelius 5\"
```

Note that the path separator has to be entered twice, e.g. C:\\Folder\\Folder.

- To specify the IP address or server name (and port, if necessary) of the Licence Server, edit:

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Sibelius Software\Sibelius 5\Preferences\LicenceServerInfo]
@=""
```

Type the IP address between the quotation marks, so the line looks like e.g. `@="192.16.1.10"`

- To specify Sibelius's serial number, edit:

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Sibelius Software\Sibelius 5\SerialNumber]
@=""
```

Type the serial number between the quotation marks. It doesn't matter whether you include spaces, but you must include the full serial number. So the line should read something like `@="SCEG 123 456 789 123456"`

Once you have edited the Registry key, you can deploy it to each of the client machines in the normal way established by your network administrator.

Note about subnet masks

A subnet mask is used on a TCP/IP network to determine which IP addresses belong to the individual network, or subnet. For example, a typical network uses IP addresses in the range 192.168.1.*n* (where *n* is an integer from 0-255); in this case, the subnet mask would be 255.255.255.0, signifying that only the last digit of the IP address of each client machine on the network may be variable. The final digit of the subnet mask address varies according to the precise range of the subnet: a value of 0 allows the full range of 0-255 to be used in the IP addresses of the client machines.

In some cases, particularly where a network uses dynamically-assigned IP addressing (via DHCP), the subnet mask on the machine running the Sibelius Licence Server may not be correctly configured to allow access by all client machines on the network.

The symptoms of this problem are as follows:

- Sibelius cannot find the Licence Server on the network, but;
- it is possible to ping the server machine from the client machine and vice versa.

If you experience the above problem, review the subnet mask settings on both machines. If your network uses a router to control access from one subnet to another, the router will take precedence over the subnet mask setting.

Security

To maintain proper security on your network, the Sibelius 5 DVD-ROM and Licence Server CD-ROM should only be used by the network administrator. Store them and this booklet in a secure place after use so that students cannot access them. Do not copy the DVD-ROM or CD-ROM – copying is illegal.

Configuring and using the Licence Server

Configuring the Licence Server

Terminology

Before we get into the details of how to configure the Licence Server, some important terms are defined here:

- *Server*: this is the Licence Server program itself, as opposed to a *service* (see below).
- *Service*: a process on your computer that runs in the background performing one or more specific tasks. Many services are started automatically when your computer runs, or when a specific user logs in. The Licence Server is intended to be run as a service, meaning that it will be started automatically when the computer is started.

Licence Server states

When the Sibelius Licence Server is running, it can be in one of four different states, which are normally passed through in order, as follows:

- *Installed*. Simply running the installer achieves this state.
- *Running the service*. The installer also automatically starts the service.
- *Registered*. You have to provide the Licence Server with its registration information (the Sibelius serial number and Registration Number) in order to move into the final state.
- *Running the server*. As soon as the Licence Server is registered, it becomes fully operational, and can authorize client copies of Sibelius.

You can stop and restart the Licence Server at any time using the Licence Server Control Panel; when you restart it, it will return to the same state as when you stopped it.


Once the Sibelius Licence Server reaches the fourth and final state (running the server), it is ready to use.

Running the Licence Server Control Panel

In order to see the status of the Licence Server and make changes to its configuration, you use the Licence Server Control Panel. You can run the Control Panel either on the same machine that the Licence Server is installed, or on another workstation. To run the Control Panel:

- On Windows, choose **Start** ▶ **Control Panel**, then double-click **Sibelius Licence Server**.
- On Mac, navigate to the **Sibelius 5 Licence Server** folder inside **Applications**, then double-click the **SibeliusLicenceServerControlPanel** icon.

The following window will appear:



As you can see, there are five pages in the Control Panel:

- **Server Status** shows the status of the server at a glance, and allows you to perform the essential configuration tasks: locating the server; starting and stopping the service (Windows only); registering the server; and starting and stopping the server.
- **Server Options** allows you to set some more advanced properties of the server, including log verbosity (i.e. how detailed the logs should be), how long the client time-out should be, and what port the server should run on. You can also run some very useful diagnostics on the Licence Server from this page.
- **Access Control** determines which computers can connect to the Licence Server, both for authorizing Sibelius clients and for determining which machines can be used to run the Control Panel to configure the server.
- **Clients** shows details of the clients that are currently connected to the server, and allows you to send messages to them, or close the clients down.
- **Log** shows the Licence Server log file, useful for diagnostics.

The options on each of these pages are discussed in detail in the following pages.

Registering the Licence Server

Connecting to the Licence Server

At the top of the **Server Status** page of the Control Panel, you can see the IP address of the Licence Server that the Control Panel is connected to:

The screenshot shows a configuration panel titled "Licence Server Address". It contains a text input field with the value "127.0.0.1:7312". To the right of the input field are two buttons: "Set..." and "Find...".

By default, the Control Panel assumes that the Licence Server is running on the same machine, which is represented by the special IP address 127.0.0.1, on the default port (7312).

You can tell whether or not the Control Panel has successfully connected to the Licence Server by reading the status message in the **Server Status** group at the bottom of the page.

If the Control Panel has successfully connected to the Licence Server, you will see the following status message:

The screenshot shows a panel titled "Server Status". The message "Licence Server is not yet registered." is displayed. Below the message are two buttons: "Start" and "Stop".

If you see this message, skip down to **Registering the Licence Server** on page 25.

Unable to connect?


If the Control Panel is unable to connect to the Licence Server, you will see the following status message:

The screenshot shows a panel titled "Server Status". The message "Licence Server is not responding." is displayed. Below the message are two buttons: "Start" and "Stop".

If you see **Licence Server is not responding**:

- Click the **Find** button at the top of the page. The Control Panel will then search your local network for running Licence Servers. If multiple running servers are found, you will be prompted to choose which Licence Server to connect to. If, on the other hand, you are told that **No Licence Servers were found on your subnet**, or if one or more servers appears, but not the one you expect to see, read on.
- Check your firewall rules. Make sure that port 7312 is open for both TCP and UDP traffic, then click **Find** again.


- If Find reports no licence servers, click Set and the following dialog will appear:



If the Licence Server is running on the same machine from which you are running the Control Panel, make sure that **Server is running on this machine (localhost)** is switched on.


If the Licence Server is running on another machine, type the IP address of the machine.

- If you still can't connect, check that the Licence Server process is running:
 - On Windows, run the **Services** management console (on Windows XP/2003, choose **Start ▶ Run**, then type **services.msc** and hit **Return**; on Windows Vista, choose **Start**, then type **services.msc** and hit **Return**). In the list of services, look for **Sibelius Licence Server V5**: check that **Status** is set to **Started**:



If **Status** is empty, then the service is not running, and you should try starting it manually – see **Appendix A: Starting or stopping the Licence Server** on page 43.

- On Mac, run Activity Monitor (from /Applications/Utilities), and make sure that the Show drop-down at the top of the window is set to All Processes. Type licence into the Filter edit box, and you should see the LicenceServer process listed:




Don't worry if the LicenceServer process is colored red and says (Not Responding). This is a quirk of how the Licence Server process appears in Activity Monitor; provided the CPU usage for the process is at a low level (e.g. below 10%), chances are everything is working fine.

If the LicenceServer process does not appear in the list, you should try starting it manually – see **Appendix A: Starting or stopping the Licence Server** on page 43.

- If all else fails, refer to the further troubleshooting steps in **Troubleshooting** on page 37.

Registering the Licence Server


To register the Licence Server, click Register. The following dialog appears:



- Type your Sibelius serial number into the Serial number edit box. Once you have typed it in correctly, the Generate Computer Number will become enabled.
- Click Generate Computer Number to generate your Computer Number. Now you should contact Sibelius registration with your serial number and Computer Number.

- When you receive your Registration Number from Sibelius registration, type it into the **Registration Number** edit box. Once you have typed it in correctly, the **OK** button will become enabled.
- Click **OK** to complete the registration: after a few moments you will be told that your registration was successful.

You will now see the following status messages at the bottom of the **Server Status** page:




Congratulations! Your Licence Server is now registered and running. Notice that you are told the total number of copies in your license (in the above example, 25 clients), and how many clients are connected at the moment (in the above example, none).


The next step is to test client-server communication with the Licence Server using the built-in testing feature.

Testing the Licence Server

Once you have registered the Licence Server, you can test client connections to the server using the Licence Server Control Panel. Choose the **Server Options** page:



To test client connections, simply set the **Number of clients to simulate**, then click **Run Test Now**. The Licence Server Control Panel will spawn the specified number of windows (so be careful not to set too high a number!), each of which pretends to be a running client copy of Sibelius. Each window has a colored background:



A green background means that the test client is running successfully. You can see a log of the communication the client has received from the server in the pane at the bottom of the test client window.

If a test client fails to connect for whatever reason, it shows a red background:



Again, you can see the reason why the test client failed to connect in the pane at the bottom of the window. In the above example, the Licence Server already had the maximum number of allowed clients connected, so it refused authorisation (hence the message **not enough licences**).

To close all the test client windows, click **Close All Test Clients**.

If no test clients can connect


If no test clients are able to connect to the Licence Server, consider the following:

- Is the Licence Server running, and if so, is it correctly registered? Check the read-out under **Server Status** on the **Status** page of the control panel.
- Is your firewall blocking communication between the Licence Server and the test clients? Make sure that the correct port (7312 by default) is open for both the TCP and UDP protocols.
- Is the Licence Server prevented from accepting client connections from the IP address of the computer you are using to test the connection? See **Access Control** on page 29.

If all else fails, consult **Troubleshooting** on page 37.

Access Control

On the Access Control page of the Licence Server Control Panel, you can set up rules about which computers on your network can connect to the Licence Server in order to authorize client copies of Sibelius or change settings for the Licence Server itself.



Clients and Managers

By now you will be familiar with the term *client*, meaning a computer on which Sibelius is installed, and which will be connecting to the Licence Server for authorization. Clients are specified by IP addresses, or ranges of IP addresses.

A *manager* is a computer from which it is possible to change settings for the Licence Server. As with clients, managers are specified by IP addresses.

Typically, you would need somewhat permissive access control for clients (because you may have Sibelius installed on every computer in the school, for example) and less permissive access control for managers (because only, say, the network administrator and the teacher's workstation should be able to change Licence Server settings).

Allow or Block

Simply put, a machine at a given IP address can connect to the Licence Server if it is set to *allow*, and cannot connect to the Licence Server if it is set to *block*.


Setting up access controls

By default, only the local machine's IP address (127.0.0.1) is given access to the Licence Server, as either a client or a manager, so the first thing you would typically need to do is set up access control for the client machines on your network.

Local area networks usually use one of three specially designated ranges of IP addresses (10.0.0 – 10.255.255.255, 172.16.0.0 – 172.31.255.255 or 192.168.0.0 – 192.168.255.255). If you

are not sure what range of IP addresses is used by your network, contact your network administrator before you proceed.

Normally you will want to grant client access to your whole subnet. For example, if the IP addresses of all your clients are in the range 172.16.0.0 –172.16.1.255, you would type 172.16.*.* into the boxes provided, as follows:



The screenshot shows a dialog box titled "Allow or Block Clients and Managers". It contains an "IP address:" field with four input boxes containing "172", "16", "*", and "*". To the right of the IP field are two rows of buttons: "Client:" with "Allow" and "Block" buttons, and "Manager:" with "Allow" and "Block" buttons. An "Apply" button is located to the right of the "Manager:" buttons.

then click the **Allow** button next to **Client**, then click **Apply** to send your changes to the Licence Server. An asterisk (*) means that the Licence Server should accept any value in the range 0–255. (You can allow client access from all IP addresses by typing *.*.* here, but this is not recommended! In general you should make network access only as permissive as necessary, and no more.)

You may need to block client access to a particular IP address or a range of machines, in which case enter the IP address as above, and click **Block**.

To grant manager access, enter the IP address as above, then click the **Allow** button next to **Manager**. You are recommended to limit manager access to only those machines that absolutely require it.

To remove a specific access control restriction, select the appropriate row in the table at the top of the page, then click **Delete**.

If at any point you want to reset the access control settings to their defaults, click **Restore Defaults**. You will be asked to confirm that you want to proceed: click **Yes**.

Working with clients

The Clients page of the Licence Server Control Panel shows real-time information about the client copies of Sibelius currently connected to the Licence Server:


Address	Client ID	Time Connected	Last Polled
127.0.0.1	12	0:01:03	11 seconds ago
127.0.0.1	11	0:01:03	4 seconds ago
127.0.0.1	10	0:01:03	11 seconds ago
127.0.0.1	9	0:01:03	7 seconds ago
127.0.0.1	8	0:01:03	8 seconds ago
127.0.0.1	7	0:01:03	7 seconds ago
127.0.0.1	5	0:01:03	15 seconds ago
127.0.0.1	4	0:01:04	9 seconds ago
127.0.0.1	3	0:01:04	11 seconds ago
127.0.0.1	2	0:01:04	7 seconds ago
127.0.0.1	1	0:01:04	11 seconds ago

- **Address** shows the IP address from which the client is connected. It is possible for multiple clients to appear to connect from the same IP address if your Licence Server is located on the opposite side of a firewall or router from your client machines, or in other situations where your network uses Network Address Translation (NAT).
- **Client ID** is a numeric identifier given to each client machine when it first connects to the Licence Server. This identifier remains associated to that client machine as long as it is connected to the server for that session, and when the client disconnects and reconnects (e.g. because a student quits and restarts Sibelius), it will be assigned a new identifier. Similarly, when the Licence Server is restarted, the client IDs are simply reassigned from 1 again. (Client IDs are used by the Licence Server to ensure that it can tell each client apart, especially when your network employs NAT.)
- **Time Connected** shows how long each client has been connected for, in hours, minutes and seconds.
- **Last Polled** shows when the Licence Server last polled the client and received a reply. Typically, clients will be polled every few seconds, and only when you suffer a network outage of some kind (or when the client computer crashes) will the client not be able to respond to the Licence Server's poll message.

In addition to seeing real-time information about the clients currently connected, you can perform some simple operations on the client machines, namely sending a message to one or more clients, or closing one or more clients.

Sending messages to clients

If you need to send a message to one or more clients, e.g. to inform them that the lesson ends in a few minutes, or that the computer lab will be closing shortly, you can select the client (by clicking) or clients (by **Shift**-clicking or using **Ctrl**+click or **⌘**-click) from the list at the top of the dialog, then click **Send Message**. A simple dialog appears:




Type your message and click **OK**. Your message will appear within a few moments on the screens of each of the clients to whom you chose to send it.

Closing clients

To close one or more client, select the client (by clicking) or clients (by **Shift**-clicking or using **Ctrl**+click or **⌘**-click) from the list at the top of the dialog, then click **Close Selected Clients**. Within a few moments, each of the client machines will prompt the student to save their work, and then shut down.

Reading logs

The Logs page of the Licence Server Control Panel shows the log messages generated by the Licence Server:



- **Time** shows the timestamp at which a given event occurred.
- **Client Address** either shows the IP address of the client machine, or if it is an informational message generated by the Licence Server itself, this will read **(Status)**.
- **Message** shows the text of the message itself. Some of the common messages you will see:
 - **Adding client id: n (x of y)**: when a client first connects to the Licence Server, it is assigned client ID n , and you are informed that this is copy number x of the number of concurrent copies allowed, y .
 - **Client add request version**: this means that a client has asked the Licence Server for authorization.
 - **Client alive**: this means that a client has been successfully authorized.
 - **Poll response from client id n** : this is the response of the client to the Licence Server's poll request.
 - **Poll count -1 for id n** : this means that client ID n has stopped responding to the Licence Server's poll requests.
 - **Removed client from list**: this means that a client has closed.


The buttons at the bottom of the page allow you to perform various operations on the log:

- **Save As**: if you encounter problems with the Licence Server, it is very useful to send your log file to Sibelius technical support. Simply click **Save As** to save a text file suitable for attaching to an email.

- **Clear** will empty the log. Note that this not only clears the display in the Licence Server Control Panel: it deletes the existing log altogether. (The log is also deleted each time you start the Licence Server.)
- **Refresh** forces the display of the log file to be updated. The display is automatically updated every few seconds, but if you want to force an update, you can do so.
- **Mark** inserts a marker line in the log file, which can be useful when trying to diagnose what the Licence Server is doing while it's running.
- **Status** inserts a status report message into the log, including important bits of configuration information (including the Licence Server's serial number, IP address and port, number of registered copies, client and manager access control lists, and so on) that can help Sibelius technical support to diagnose any problems you may encounter.
- **Comment** shows a simple dialog into which you can type a comment to be inserted in the log file. You can use this to annotate a sequence of events in the log; again, this can be very useful in helping Sibelius technical support to diagnose problems.

Log verbosity

You can control how detailed the Licence Server logs are by adjusting the slider on the **Server Options** page of the Licence Server Control Panel:



While you are configuring and testing your Licence Server, you may find it helpful to drag the slider to the right to increase the verbosity. Once your Licence Server is running smoothly, you can safely drag the slider back to the left in order to make the logs more concise.


Maintaining the Licence Server

There are a handful of other maintenance tasks that can be performed from the Licence Server Control Panel, described below.

Changing the port used by the Licence Server

The Licence Server's default port is 7312. There is normally no need to change this, and we recommend that you leave this setting at its default.

If, however, you need to change the port, click **Change Port** on the **Server Options** page of the Licence Server Control Panel. The following dialog appears:



As the message in the dialog makes clear, changing the port after you have already set up your Licence Server can be very inconvenient, because you need to reconfigure each client machine to use the new port afterwards.

Changing the number of copies in an existing site licence

If you decide to increase the number of copies in your Sibelius network site licence, you will need to unregister your Licence Server and obtain a new Registration Number from Sibelius registration.

To unregister your Licence Server, click **Unregister** on the **Status** page of the Licence Server Control Panel. You will be asked if you are sure you want to unregister the Licence Server: if you click **Yes**, the Licence Server will become unregistered, and it will no longer be able to authorize any client copies of Sibelius.

To re-register your Licence Server with a larger number of copies, follow the procedure described in **Registering the Licence Server** on page 23.

Unexpected exits

In the unlikely event that a copy of Sibelius running on a client machine exits unexpectedly (e.g. if it crashes), or if the computer on which Sibelius is running crashes or requires a reboot, when the student runs Sibelius again, the Licence Server will attempt to identify that the same client is reconnecting, and re-authorize it immediately. If, however, the Licence Server is unable to recognize the client, the student may see the error message **Sibelius cannot run because the server already has a copy registered on this address**. In this situation, the student can wait for the designated time-out period, and he or she will then be able to successfully restart Sibelius.

By default, the time-out period is three minutes, but you can change this on the **Server Options** page of the Licence Server Control Panel:



Simply drag the slider to the right to increase the time-out period, or to the left to reduce it.

Troubleshooting

Error codes

For a complete list of the error codes that can be returned by the Licence Server, see **Appendix E: Licence Server error codes** on page 51.

Error message 'unable to bind sockets' (Windows XP)

If you get the error message `Unable to bind sockets`, check your firewall settings (in **Start ▶ Control Panel ▶ Network Connections**).

Error 0005 Access Denied

If the Licence Server service in Windows fails to start automatically, you may get an **Error 0005 Access Denied** when you try to start it manually. This usually means that the folder in which the Licence Server is installed has restricted access.

Licence Server is apparently installed correctly but the clients cannot "see" the Licence Server

- Open a command window (Windows) or Terminal window (Mac) and use `ping` to contact the server from the client and vice versa to establish basic connectivity. If `ping` is successful in both directions, network traffic is able to be routed between the two machines. If `ping` fails, it's possible that another device on the network (e.g. a programmable switch) is blocking the traffic between the Licence Server and the client. Check the logs to see if you are getting an "extra slave alive" message.
- Review your access settings using the **Access Control** page of the Licence Server Control Panel – see **Access Control** on page 29.
- This can also be caused by your firewall. Try this trick: if you are running the Control Panel on the same machine as the Licence Server, add the server's IP address to the list of allowed managers, then connect to the server by IP address (or use the **Find** button). If you are unable to connect or test the server in this way, it suggests that the firewall on your local machine is not allowing connections through on the Licence Server's port. If you are able to test the server but other clients still can't connect, then check the settings of any other firewalls or routers on your network.

Error message 'Could not bind the IP socket to the correct port'

If you see the error message `Could not bind the IP socket to the correct port` when running the Licence Server, you may be running another application on this port already. You may even be running the Licence Server already: perhaps you are running the Sibelius 3 or Sibelius 4 Licence Server at the same time as the Sibelius 5 Licence Server, or perhaps the Licence Server has crashed and the crashed process needs to be killed before it can be restarted.

If you legitimately have another application using the same port, you can solve this problem changing the Licence Server's port (see **Changing the port used by the Licence Server** on page 35).

Client copies of Sibelius on Mac lose contact with the Licence Server

Make sure that your server is not allowed to go to “sleep” as this will stop the Licence Server from responding. You should also ensure that your server does not install software updates automatically, as this will also stop the Licence Server from responding.

Licence Server receives messages but client doesn't "see" Licence Server

This can be caused by the firewall settings in Windows XP Service Pack 2. Turn the firewall off to check this and, if this works, add an appropriate exception to the firewall rules. A clue to this problem is found when viewing the log: you will see `slave alive` followed by an `extra slave alive` message.

This should not happen with the Sibelius 5.1 Licence Server, as it has been written specifically to allow client copies to connect through a firewall.

Licence Server fails to test successfully

Did you forget to include the localhost, 127.0.0.1 in your clients allowed access control list?

Using the log to troubleshoot

The log can be very informative when investigating a client that fails to be authorized. Here are some examples.

First, a client with the wrong serial number attempting to be authorized:

```
(243) 172.24.166.153(2851) : Client alive
(243) 172.24.166.153(2851) : Client add request version: 5, protocol: 2000, uid:
, machineID: -54048230, serial: SCEW410238656340057
(243) 172.24.166.153(2851) : Bad serial number SCEW410238656340057
```

Next, a client with the wrong version of Sibelius installed attempting to be authorized:

```
(243) 172.24.166.153(2851) : Client alive
(243) 172.24.166.153(2851) : Client add request version: 5, protocol: 2000, uid:
, machineID: -54048230, serial: SCEW410238656340057
(243) 172.24.166.153(2851) : Bad serial number SCEW410238656340057
(369) 172.24.166.153(2852) : Client alive
(369) 172.24.166.153(2852) : Bad version number 4
(372) 172.24.166.153(2852) : Client alive
(372) 172.24.166.153(2852) : Bad version number 4
(375) 172.24.166.153(2852) : Client alive
(375) 172.24.166.153(2852) : Bad version number 4
```

Note also that the client had Sibelius 5.0 installed. The message `Client alive` indicates that a client is trying to get authority to run. (Clients running Sibelius 5.0 can be authorized by the Sibelius 5.1 Licence Server, but clients running Sibelius 5.1 cannot be authorized by the Sibelius 5.0 Licence Server.)

Finally, a client is blocked because there are no more available licences:

```
(440) 172.24.166.167(51799) : Client alive
(440) 172.24.166.167(51799) : Client add request version: 5, protocol: 2000, uid
: , machineID: 09798819, serial: SCEW410190760340058
(440) 172.24.166.167(51799) : New client at this address
(440) 172.24.166.167(51799) : Blocked client, no copies left
(451) 172.24.166.155(2606) : poll count -1 for id 2
(452) 172.24.166.158(50041) : poll count -1 for id 1
(453) 172.24.166.158(50041) : Poll response from client id 1
(454) 172.24.166.155(2606) : Poll response from client id 2
(464) 172.24.166.158(50041) : poll count -1 for id 1
(468) 172.24.166.158(50041) : Poll response from client id 1
(470) 172.24.166.155(2606) : poll count -1 for id 2
(474) 172.24.166.155(2606) : Poll response from client id 2
```

Appendices


Appendix A:

Starting or stopping the Licence Server

Normally you should use the Licence Server Control Panel to start and stop the Licence Server. But should you need to start or stop the Licence Server without using the Control Panel, you can do so as follows:

Starting the Licence Server on Windows

- First, open a command prompt window:
 - *On Windows XP/2003:* choose **Start** ▶ **Run**, then type `cmd` and hit **Return**;
 - *On Windows Vista:* click **Start**, type `cmd` and hit **Return**.
- This opens a command shell window:



- Navigate to the folder where you installed the Licence Server using `cd`:
cd \Program Files\Sibelius Software\Sibelius 5 Licence Server
 Make sure you type the line above exactly, with spaces in all the right places. You will be returned to the command prompt in the above directory.
- Now, to install the service, type:
LicenceServerV5 -install
- You will see the following response from the Licence Server:

```
Could not find service to uninstall
Service started okay
U4 server running: no
U5 server running: yes
```

- You will again be returned to a command prompt.

Stopping the Licence Server on Windows

- First, open a command prompt window:
 - *On Windows XP/2003:* choose **Start** ▶ **Run**, then type `cmd` and hit **Return**;
 - *On Windows Vista:* click **Start**, type `cmd` and hit **Return**.
- This opens a command shell window. Navigate to the folder where you installed the Licence Server using `cd`:
cd \Program Files\Sibelius Software\Sibelius 5 Licence Server
Make sure you type the line above exactly, with spaces in all the right places. You will be returned to the command prompt in the above directory.
- Now, to install the service, type:
LicenceServerV5 -uninstall
- You will again be returned to a command prompt.

Starting the Licence Server on Mac OS X

- Open a Terminal window and log in as root by typing:
sudo bash -login
- Type the root password when prompted, and hit **Return**.
- Now type the following command:
/sbin/SystemStarter -v start "Sibelius 5 Licence Server Service"

Stopping the Licence Server on Mac OS X

- Open a Terminal window and log in as root by typing:
sudo bash -login
- Type the root password when prompted, and hit **Return**.
- Now type the following command:
/sbin/SystemStarter -v stop "Sibelius 5 Licence Server Service"

Appendix B:

Manually configuring the Licence Server

Normally you should use the Licence Server Control Panel to configure the Licence Server, but should you need to do this without using the Control Panel, you can do so as follows:

Checking the status of the Licence Server

You can check the server's status at any time by running the `-query` command from the command line.

On Windows, refer to the instructions **Starting the Licence Server on Windows** on page 43 for how to type commands for the Licence Server. Then type:

```
LicenceServerV5 -v -query
```

On Mac, open a Terminal window, then type:

```
cd "/Applications/Sibelius 5 Licence Server/"
```

to change to the directory where the Licence Server executable is located. Now type:

```
./LicenceServer -v -query
```

(Note that you must always prepend commands to the Licence Server with `./`, which tells the Terminal that the command you're running is a program.)

This will elicit the following response from an unregistered Licence Server:

```
Licence server version Version 5.1.5 - For use with Sibelius 5 only  
state: UNREGISTERED copies: 0/-1 serial: , up 0:01:00
```

Registering the Licence Server

To register the Licence Server, you must first enter your serial number. Note the use of quotation marks. On Windows, type:

```
LicenceServerV5 -setvar SERIAL "SCEW 123 456 789 123456"
```

On Mac, type:

```
./LicenceServer -setvar SERIAL "SCEW 123 456 789 123456"
```

entering your own serial number between the quotation marks. Note that the arguments are case-sensitive, so you should be careful to type them correctly.

The response will be:

```
Set variable SERIAL = SCEW 123 456 789 123456
```

The next step is to register the Licence Server, and for this you will need the Computer Number. To get it, on Windows type:

```
LicenceServerV5 -getvar COMPUTER_NUMBER
```

On Mac, type:

```
./LicenceServer -getvar COMPUTER_NUMBER
```

The response will be:

```
Got variable COMPUTER_NUMBER = C 1234 5678 1234 5678
```

You then need to contact Sibelius registration, quoting your serial number and Computer Number to obtain your Registration Number.

You can then register as follows, once again taking care with quotation marks. On Windows, type:

```
LicenceServerV5 -setvar REGISTRATION_NUMBER "R 8765 4321 8765 4321"
```

On Mac, type:

```
./LicenceServer -setvar REGISTRATION_NUMBER "R 8765 4321 8765 4321"
```

The response will be:

```
Set variable REGISTRATION_NUMBER = R 8765 4321 8765 4321
```

If this is successful then the `-query` command should report the server as being in the *configuring* state. The response will be:

```
Licence server version Version 5.1.5 - For use with Sibelius 5 only  
state: CONFIGURING copies: 0/10 serial: SCEW 123 456 789 123456, up 1:02:07
```

This tells you that the Licence Server is in *configuring* mode, 0 out of 10 copies are licenced, and it has been running for 1 hour, 2 minutes and 7 seconds.

Access controls and other settings

Next, set the access control lists. These are the IP addresses of the client computers that will apply to the Licence Server for authorization, and can be entered as a range using the wildcard `*`, e.g., `192.168.*.*` will allow any client in any subnet of the `192.168` local network to “see” the Licence Server. The IP address part of the argument must be enclosed in quotation marks. Failure to use quotation marks will result in an incomplete state which will need you to type `Ctrl+C` (Windows) or `Control-C` (Mac) to exit.

The arguments can be:

- `ALLOWED_CLIENTS`
- `ALLOWED_MANAGERS`
- `BLOCKED_CLIENTS`
- `BLOCKED_MANAGERS`

Reminder: an argument is a qualifier that can be applied to a command (`-setvar` in this instance). Any previous settings will be replaced by the new information that you enter in quotation marks, so always remember to include the local machine’s address (`127.0.0.1`), else you will not be able to execute the `-test` command.

So to allow localhost (`127.0.0.1`) and all machines on the subnet `172.24.170.*` access to the Licence Server, on Windows type:

```
LicenceServerV5 -setvar ALLOWED_CLIENTS "127.0.0.1,172.24.170.*"
```

On Mac, type:

```
./LicenceServer -setvar ALLOWED_CLIENTS "127.0.0.1,172.24.170.*"
```

to which the response will be:

Set variable `ALLOWED_CLIENTS = 127.0.0.1,172.24.170.*`

To check your access control settings, use the `-getvar` command. On Windows, type:

```
LicenceServerV5 -getvar ALLOWED_MANAGERS
```

On Mac, type:

```
./LicenceServer -getvar ALLOWED_MANAGERS
```

to which the response will be something like:

Got variable `ALLOWED_MANAGERS = 127.0.0.1`

To check which machines are allowed as clients, on Windows type:

```
LicenceServerV5 -getvar ALLOWED_CLIENTS
```

On Mac, type:

```
./LicenceServer -getvar ALLOWED_CLIENTS
```

to which the response will be something like:

Got variable `ALLOWED_CLIENTS = 127.0.0.1,172.24.170.*`

Appendix C:

Manually locating Licence Server logs

Normally you should view the Licence Server's logs using the Licence Server Control Panel, but should you need to do this manually, do so as follows.

Logging on Windows

The Licence Server creates a log file called `LicenceServerV5.log`. The log file is normally located in:

- *Windows 2003 Server:* `C:\Documents and Settings\Default User\Application Data\Sibelius Software\Logs`
- *Windows XP:* `C:\Documents and Settings\LocalService\Application Data\Sibelius Software\Logs`
- *Windows Vista:* `C:\Users\LocalService\AppData\Roaming\Sibelius Software\Logs`

The exact location depends on your computer's settings, so it may be necessary to search for the folder. The logs are updated with every event.

Logging on Mac OS X

The Licence Server creates a log file in `/var/log` called `LicenceServer.log` (unless you have changed its name and location in the `start_licence_server` script). To see the last few entries in the log, open a Terminal window and navigate to the `/var/log` folder or the folder you have specified for the log file. Assuming you are using the default filename, type:

```
tail -f LicenceServer.log
```

To quit the `tail` command, type `Control-C`. To view the whole log, use the `less` command:

```
less LicenceServer.log
```

Quit the `less` command by typing `q`.

Appendix D: Licence Server commands

The following commands can be used from the command line:

Set-up commands (accessible only from the local machine):

-help or -h	Displays the complete list of Licence Server commands
-v or -vv	Verbose or very verbose output
-version or -V	Displays the Licence Server version number

Windows-specific service options

-install	Installs as a Windows service
-uninstall	Stops and uninstalls Windows service
-startservice	Starts the Windows service
-stopservice	Stops the Windows service
-noservice	Don't try to start the service when run from the foreground

Management commands – for communicating with a running service

-localstatus	Show status of running Licence Server(s) on local machine
-test [server] [serial number]	Simulate connection and authorization request from a client
-testloop [server] [serial number]	Simulate connection and authorization request from a client, and continue polling.
-test50 [server] [serial number]	Simulate connection and authorization request from a Sibelius 5.0 client
-testloop50 [server] [serial number]	Simulate connection and authorization request from a Sibelius 5.0 client, and continue polling.
-query machine	Get information on Licence Server on <i>machine</i> (IP address)
-kick all	Close all clients
-kick address	Close client on IP address <i>address</i>
-kick address:port	Close client with this IP address/port number
-kick address server	Close clients on this server
-warn "message" address[:port]	Warn clients on this address/port
-warn "message"	Display this warning message on all clients. Message must be in quotation marks.
-dumplog filename [server]	Writes the server's log to a local filename
-getvar variable [server]	Get the specified <i>variable</i> from the server
-setvar variable value [server]	Set the <i>variable</i> to the specified <i>value</i> on the server
-start [server]	Start the server (if in <i>configuring</i> state). On Mac, the daemon has to be started first using the script <code>start_licence_server</code> , else this command has no effect.
-stop [server]	Stop the server (and return to <i>configuring</i> state).
-unregister [server]	Unregister the server, so that you can re-register (e.g. to change the number of copies the server can authorize). On Mac, you <i>must</i> run the script <code>reload_licence_server</code> in order for the server to recognise the new number of copies.
-discover [broadcast mask] [port]	Look for any servers running on the local subnet. If set, the <code>LS_HOST</code> environment variable is used by default. You can set this using the command <code>set LS_HOST server</code> .

Variables – for use with -getvar and -setvar

SERIAL	Serial number, required for registration (get only)
COMPUTER_NUMBER	Computer Number, required for registration (get only)
REGISTRATION_NUMBER	Registration Number, required for registration (set only)
ALLOWED_CLIENTS	Comma-separated list of IP addresses that are allowed to connect to the server for authorization
BLOCKED_CLIENTS	Comma-separated list of IP addresses that are prohibited from connecting to the server
ALLOWED_MANAGERS	Comma-separated list of IP addresses that are allowed to configure the server
BLOCKED_MANAGERS	Comma-separated list of IP addresses that are prohibited from configuring the server
PORT	The port on which the server is running (requires server restart)
TIMEOUT	How long the server should wait for a poll to be returned by a client, in seconds.
VERBOSITY	The verbosity level of the server.

Appendix E: Licence Server error codes

<i>Error code</i>	<i>Internal error message</i>	<i>Explanation</i>
301	ERR_LS_CANT_CONNECT_TO_SERVER	The service is not yet running
302	ERR_LS_AUTH_NO_MORE_COPIES	No more licences left on server
303	ERR_LS_AUTH_ALREADY_RUNNING_THIS_IP	A version is already running at this address
304	ERR_LS_AUTH_DENIED	Can't authorize this client
305	ERR_LS_SHUTDOWN	Server has requested that we shut down
306	ERR_LS_INCORRECT_SIB_VERSION	Licence Server is for a different version of Sibelius.
307	ERR_LS_OLD_LS_VERSION	Using the wrong version of the Licence Server
308	ERR_LS_CLIENT_COMM_ERROR	Can't communicate with client
309	ERR_LS_INVALID_SERIAL	Invalid serial number
310	ERR_LS_NO_ACCESS	No access control has been set up
311	ERR_LS_SOCKET_FAIL	Can't create or bind network sockets
312	ERR_LS_SERVICE_CANT_FIND_MODULE	Can't find LicenceServerV5 executable to install as a service (Windows only)
313	ERR_LS_SERVICE_CANT_OPEN_SERVICEMAN	Can't open the service manager (Windows only)
314	ERR_LS_SERVICE_CANT_CREATE_SERVICE	Can't create the service (Windows only)
315	ERR_LS_SERVICE_CANT_START	Error starting the service (Windows only)
316	ERR_LS_SERVICE_CANT_OPEN	Error opening the service (Windows only)
317	ERR_LS_GENERAL_ERROR	General error from the Licence Server

Appendix F:

Useful command line commands

Useful Mac OS X Terminal commands

- `chmod` – used to change the attributes of a file
- `ls -al` – lists all the files in a directory with their attributes
- `ps -a` – lists running processes, which will include the Licence Server
- `ps -ax` – lists all running processes, including hidden ones.
- `mkdir -m 775 name` makes a directory called *name* with full read/write access for the owner and their group (typically the admin group), but prevents write access for other users.
- `tail -f logfile` will display the last 10 lines of the log file *logfile* continually; useful for monitoring client messages.
- `less logfile` will display the whole log file *logfile* from beginning to end; quit by typing `q`.
- `cd` changes the current directory
- `pico` starts the Pico text editor (if installed)
- `logout` will log out from the current user, e.g. root. (You can also type `Control-D`.)
- `./filename` will run an executable or script called *filename* in the current directory, provided you are using bash or a bash-compatible shell (as suggested earlier). Once unique characters have been typed, the `Tab` key will auto-complete the rest of the file name for you.
- To quit a running command, type `Control-C`.

Useful Windows/DOS commands

- `cd` – change directory (the old name for folder).
- `cd ..` – moves to the next higher directory. If you repeat this enough times, you will get back to the root of the hard disk.
- `cd \` – moves you to the root directory.
- `cd \dirname` – takes you to the directory called *dirname*. If you copied the Licence Server program to a folder named LSV5 (for example) then `cd \LSV5` will get you there.
- `dir` – lists the contents of a directory. Use this to check that you are in the right directory.
- `exit` – closes a command prompt window.
- To quit a running command, type `Ctrl+C`.